



Aysa Trade

User guide — Professional trade management for MetaTrader 5

v2.4.1 • aysatrade.ir

Contents

1. Installation
2. The panel and the Trade page
3. Position tool on the chart (Lines)
4. Draw a trade
5. Close page
6. Trail page (trailing stop)
7. BE/Lim page
8. Setup page
9. Parts page (partial close)
10. Time page
11. Prop page (prop-firm guard)
12. Emergency Auto Pilot (Pilot)
13. Info page and news warning
14. Colors and the Custom theme
15. Important notes

Full guide

Section by section, with a picture of every panel page.

01 Installation

1. Download `AysaTrade.ex5` with the "Download the EA" button on **aysatrade.ir** and copy it into the `MQL5\Experts` folder of MetaTrader (File › Open Data Folder).
2. In the Navigator, right-click Expert Advisors and choose Refresh.
3. Drag AysaTrade onto a chart. On the Common tab enable **Allow Algo Trading**.
4. The **Algo Trading** button in the MetaTrader toolbar must be on as well.

The main settings (help language, theme, magic number, hotkeys and defaults) are on the Inputs tab. Most settings are later changed on the panel itself and are remembered.

02 The panel and the Trade page


Header: logo and version, **Shot** for a screenshot and _ to minimize. Drag the header to move the panel.

Symbol row: symbol name (type and press Enter to change), previous / next symbol, **All charts** to change every chart at once, broker time (Brk) and local time (Loc).

Tabs: Trade, Close, Trail, BE/Lim and Setup. Parts, Time, Prop, Pilot, Info and Colors open from Setup.

Trade page fields

- **Risk** and its method: fixed money or percent of balance, equity, free margin, a custom base or the balance at the start of the day/week/month.
- **Lot:** calculated from the risk and the SL distance when **Lot calc** is on.
- **Entry:** distance of a pending order from the price (points). **SL** and **TP** in points; **Price** switches them to prices.



- **R/SL** and **R/TP**: with **RR** on, the TP is built from this ratio.
- **Note**: order comment; the default is the EA name and version.
- **Market / Stop / Limit** and **Virtual** (a pending order kept inside the EA).
- **Sell / Buy**: if the SL is above the entry only Sell is enabled, and vice versa.
- **OCO (Stop)**: a buy stop and a sell stop; when one is filled the other is deleted. Both use the SL and TP boxes, and the Entry box for the distance.
- **S/R alert**: alert when a candle closes across lines you drew yourself.
- The **pencil** icon: draw a trade with the mouse (see below).

When the symbol has an open trade or a pending order, the management buttons appear automatically: close sells / all / buys, delete orders, close a percentage, **Breakeven**, **+ Commission & Swap** and the **Emergency Auto Pilot** button.

Footer: risk in money, loss at SL, margin, spread and the remaining prop-firm limit.

03 Position tool on the chart (Lines)


Turning on **Lines** builds the position tool at the current price: SL from the SL box, TP from RR. Every box can be dragged:

- **Up/down** changes the price, **left/right** only moves the box. The first clear mouse movement locks the axis so a price never changes by accident.
- Dragging the entry away from the price turns the order into a Stop or Limit; near the current price it snaps back to Market.
- The **R** button reverses Buy and Sell. The **L** buttons lock SL and TP against automatic changes; the mouse can still move them.
- Faint dotted guide lines show the levels across the candles. The part of a box under the dashboard or outside the chart is hidden.

Open trades and pending orders

Every trade and order uses the same tool. The entry of an open trade is fixed; its SL and TP can be dragged and the figures update while you drag. Pending-order prices are changed only from ... > Edit. Clicking the entry bar hides or shows SL and TP. The ... menu offers Delete, Hide SL TP, OCO, Expiration, Edit, Trailing, Break Even, Partial Close, Color and Comment.

When trailing or breakeven is active, a blue "Trail start" and an orange "Breakeven at" label appear on the trade; drag them (between entry and TP) to change them. They disappear once the function has started.




Position tool on the chart (Lines)

04 Draw a trade

Click the pencil icon (or Ctrl+Shift+Q), drag on the chart from the entry to the SL and release. While dragging you see the direction, SL distance, lot and TP. The lot comes from the risk and the TP from RR. Starting near the current price gives a Market order; otherwise a Stop or Limit. The line stays until the order is filled or deleted.


05 Close page

Close buys, sells, profitable, losing or all positions, with the profit, percent and count of each group. Delete pending orders by type. **All symbols** and **All magics** set the scope. At the bottom: close everything automatically when the total profit or loss reaches an amount or a percent.




06 Trail page (trailing stop)

Seven trailing types: Pips, Fractals, Moving Average, Parabolic SAR, ATR, Partial close and High-Low bars. Only the parameters the selected type uses are shown. The unit can be **Points** or **R**; R is the initial SL distance of that trade (Start = 1.5R means when the profit reaches 1.5 times the risk).



07 BE/Lim page

Breakeven+: after the given profit the SL moves to the entry (plus the locked profit). With **+ Commission & Swap** the round-trip commission and negative swap are covered too. The spread is not needed because the MetaTrader entry price already contains it. **Limit trailing**: limit orders follow the price at the same distance. **Virtual SL/TP**: stops are not sent to the broker.




08 Setup page

Buttons for Parts, Time, Prop, Pilot and Info; theme and the Colors button; the % Custom base; slippage; **Help language**: switches the help texts, tooltips and messages between English and Persian at once (the panel buttons stay in English); order confirmation, sounds, automatic screenshots, hotkeys, trade visuals and the news warning (importance, minutes before, currencies).


Key	Action
Ctrl+Shift+U	Buy
Ctrl+Shift+J	Sell
Ctrl+Shift+X	Close all
Ctrl+Shift+V	Lines on/off
Ctrl+Shift+Q	Draw trade

These letters do not clash with MetaTrader's own shortcuts and can be changed in the Inputs.



09 Parts page (partial close)

Up to five TP and five SL levels with a volume percent and a distance (points or R; zero = evenly spaced). **SL to BE after TP1** moves the stop to breakeven after the first profit level. **Apply to open** applies the plan to open trades.



Aysa Trade v2.4.1 Shot _

XAUUSD@ < > All charts Brk 19:01:49 Loc 19:31:51

Trade Close Trail BE/Lim Setup

TP in parts SL in parts

Level	% vol	Points	Level	% vol	Points
TP1	0	0	SL1	0	0
TP2	0	0	SL2	0	0
TP3	0	0	SL3	0	0
TP4	0	0	SL4	0	0
TP5	0	0	SL5	0	0

SL to BE after TP1 Apply to open

Distance unit Points R


0 = auto (evenly spaced in TP/SL).
Toggle ON = plan for every new position.

Help language: English

Parts page (partial close)

10 Time page

Schedule a buy, sell, close buys / sells / all, delete orders or close MetaTrader at a server time, with weekly repeat.



Aysa Trade v2.4.1 Shot _

XAUUSD@ < > All charts Brk 19:01:50 Loc 19:31:52

Trade Close Trail BE/Lim Setup

Time 2026.10.09 19:06 Now +5m

Action Buy Add


Repeat Mo Tu We Th Fr Sa Su

Help language: English

Time page


11 Prop page (prop-firm guard)

- **Daily loss** and **Max loss** in percent or money; the max limit can be Static or Trailing; the day base is the balance or the higher of balance and equity.
- **Max open risk**: total loss of all trades and orders if every SL is hit; an order that exceeds it is blocked.
- **Min hold, profit**: a profitable trade is not closed before this many seconds; a timer shows on the trade box.
- Warning and action at a percent of the limit; the action closes everything and blocks trading until the next day, or only alerts.
- Live status: day base, daily floor, remaining room, open risk, profit target and progress.




12 Emergency Auto Pilot (Pilot)

For when you cannot watch the trade. One button for every trade of the symbol: partial close at 1R, breakeven, trailing (in R), profit lock, a floating-loss cap, a time action (close all or breakeven, optionally Fridays only), deleting pending orders, adding an SL to trades without one and sending events to your phone.



13 Info page and news warning


Info: account, balance, equity, margin, today's result, symbol specification and trade counts. News warning: before important events of the MetaTrader calendar a red bar with the event name and a countdown appears at the bottom of the dashboard.



Info page and news warning

14 Colors and the Custom theme

Every color, from the panel and buttons to the chart tools, trailing lines and the news bar, can be set as #RRGGBB or R, G, B. Editing any color switches the theme to Custom.



Colors and the Custom theme

15 Important notes

- Virtual orders, virtual SL/TP and the auto pilot work only while MetaTrader and the EA are running.
 - Times are broker server time; distances are points or R.
 - Always test on a demo account first.
-